

Getting Started with *insilico*IDE 1.4 CLI

In this document, we make Bonhoeffer van der Pol model (BVP) model in insilico terminal. Each section is same as Getting Started with Model Editor 1.4 vesion.

Initial settings

Create handlers and set prefix 'm' at MathML tag.

Set prefix 'm' at MathML tag (e.g. `<m:math>`, `<m:apply>`)

```
>>> cstr2mml.set_ns_prefix("m")
```

At insilico terminal, users access *insilico*ML through handlers.

This document uses the following handlers. "model" means model-handler.

When users start insilicoIDE, this model-hanlder is created automatically.

Create handlers

```
>>> hh = model.get_header_handler()
>>> mh = model.get_module_handler()
>>> ph = model.get_port_handler()
>>> eh = model.get_edge_handler()
>>> pqh = model.get_physicalquantity_handler()
>>> dh = model.get_definition_handler()
>>> dih = model.get_definition_initialvalue_handler()
>>> aih = model.get_article_info_handler()
>>> cih = model.get_creator_info_handler()
>>> uh = model.get_unit_handler()
>>> bl = model.get_builder()
>>> conv = model.get_converter()
```

File Operations

Following commands are related to file operations.

Open *insilico*ML model

Open *insilico*ML model from the file path: `sample/ SimulateWithISSim / HodgkinHuxley_1952_neuron_model.isml`

```
>>> model.load_new_isml_model("sample/SimulateWithISSim/HodgkinHuxley_1952_neuron_model.isml")
```

Save *insilico*ML model

Dump and Save *insilico*ML model to the file path: sample/SimulateWithISSim/test.isml

```
>>> save_file("sample/SimulateWithISSim/test.isml", model.dump_document())
```

Export As Other Format

Export as FreeFem

```
>>> conv.isml2ffem("sample/test.edp")
```

Export as CellML

```
>>> save_file("sample/test.cellml", conv.isml2cellml(model.dump_document()))
```

Export as TeX

```
>>> conv.isml2tex("sample/test.tex")
```

Export as Graph

```
>>> conv.isml2dot("sample/test.dot", "title")
```

Export as C++

```
>>> conv.isml2cpp("sample/test")
```

Export as Java

```
>>> conv.isml2java("sample/test")
```

Execute a Python Script File

insilico terminal is possible to execute a Python script file.

Select a python script file from the menu [Script]-[Open Script...] (Fig. 1), then the script is executed.




Fig. 1 : Open a Python script file.

1. Edit Header

1.1. Edit model name

Set model name

```
>>> hh.set_name("Bonhoeffer van der Pol model")
```

1.2. Edit numerical configurations

Get the id of the unit "millisecond"

```
>>> uid_ms = uh.get_id_with_name("millisecond")
```

Set time step 0.001 (milli second) for numerical integration

```
>>> hh.set_time_discretization(uid_ms, "0.001")
```

Set simulation time span 100 (milli second) for numerical integration

```
>>> hh.set_simulation_time_span(uid_ms, "100")
```

1.3. Edit article information

Create new article

```
>>> aid = aih.create()
```

Get PubMed information of the article from TogoWS *If your machine is not connected to internet, skip this command*

```
>>> aih.setup_pubmedinfo_from_togows(aid, "19431309")
```

1.4. Edit creator information

Create new creator

```
>>> cih.create()
```

Set each creator informaiton

```
>>> cih.set_person_name("1", "Yoshiyuki", "", "Asai")
```

```
>>> cih.add_affiliation("1", "Osaka University")
```

```
>>> cih.set_affiliation_address("1", "Osaka University", "1-1 Suita, Osaka, Japan")
```

2. BVP_excitation module

2.1. Make BVP_excitation module

Create a new module with name “BVP_excitation”

```
>>> m_bvp_x = mh.create("BVP_excitation")
```

2.2. Edit ports

Create input port Iext

```
>>> p_Iext = ph.create(m_bvp_x, "in", "Iext")
>>> ph.set_description(m_bvp_x, p_Iext, "Stimulation from external source")
```

Create input port y_i

```
>>> p_y_i = ph.create(m_bvp_x, "in", "y_i")
>>> ph.set_description(m_bvp_x, p_y_i, "Refractoriness of the ipsilateral side")
```

Create output port x

```
>>> p_x = ph.create(m_bvp_x, "out", "x")
>>> ph.set_description(m_bvp_x, p_x, "Output excitation level of this BVP")
```

2.3 Edit physical-quantity

2.3.1 x

Create physical-quantity “x” and set each property

```
>>> pq_x = pqh.create(m_bvp_x, "x")
>>> pqh.set_type(m_bvp_x, pq_x, "state")
```

Set initial-value definition of x

```
>>> mathml = cstr2mml.cstr2mml('x = 0.2')
>>> dih.set_definition(m_bvp_x, pq_x, '0', mathml, 'ae')
```

Set implementation definition of x

```
>>> mathml = cstr2mml.cstr2mml('diff(x, time) = c * ( ( x - x * x * x/3.0 - y_i ) + Iext ) ')
>>> dh.set_definition(m_bvp_x, pq_x, '0', mathml, 'ode', '')
```

Bind physical-quantity x to the output port x

```
>>> ph.set_reference(m_bvp_x, p_x, pq_x)
```

2.3.2 c

Create physical-quantity “c” and set each property

```
>>> pq_c = pqh.create(m_bvp_x, "c")
>>> pqh.set_type(m_bvp_x, pq_c, "static-parameter")
```

Set implementation definition of c

```
>>> mathml = cstr2mml.cstr2mml('c = 1.75')
>>> dh.set_definition(m_bvp_x, pq_c, '0', mathml, 'ae', '')
```

2.3.3 y_i and Iext

Create physical-quantity “ y_i ” and set each property

```
>>> pq_y_i = pqh.create(m_bvp_x, "y_i")
>>> pqh.set_type(m_bvp_x, pq_y_i, "variable-parameter")
```

Set implementation definition of y_i

```
>>> dh.set_definition(m_bvp_x, pq_y_i, '0', p_y_i, 'assign', 'port')
```

Create physical-quantity “Iext” and set each property

```
>>> pq_Iext = pqh.create(m_bvp_x, "Iext")
>>> pqh.set_type(m_bvp_x, pq_Iext, "variable-parameter")
```

Set implementation definition of Iext

```
>>> dh.set_definition(m_bvp_x, pq_Iext, '0', p_Iext, 'assign', 'port')
```

3. BVP_refractoriness module

In this section, make BVP_refractoriness module same as section2.

Make BVP_refractoriness module

```
>>> m_bvp_y = mh.create("BVP_refractoriness")
```

Input port x

```
>>> p_x_i = ph.create(m_bvp_y, "in", "x_i")
>>> ph.set_description(m_bvp_y, p_x_i, "Excitation level of the ipsilateral side")
```

Output port y

```
>>> p_y = ph.create(m_bvp_y, "out", "y")
>>> ph.set_description(m_bvp_y, p_y, "Output refractoriness of this BVP")
```

Physical-Quantity a

```
>>> pq_a = pqh.create(m_bvp_y, "a")
>>> pqh.set_type(m_bvp_y, pq_a, "static-parameter")
>>> mathml = cstr2mml.cstr2mml('a = 0.7')
>>> dh.set_definition(m_bvp_y, pq_a, '0', mathml, 'ae', '')
```

Physical-Quantity b

```
>>> pq_b = pqh.create(m_bvp_y, "b")
>>> pqh.set_type(m_bvp_y, pq_b, "static-parameter")
>>> mathml = cstr2mml.cstr2mml('b = 0.675')
>>> dh.set_definition(m_bvp_y, pq_b, '0', mathml, 'ae', '')
```

Physical-Quantity c

```
>>> pq_c = pqh.create(m_bvp_y, "c")
>>> pqh.set_type(m_bvp_y, pq_c, "static-parameter")
>>> mathml = cstr2mml.cstr2mml('c = 1.75')
>>> dh.set_definition(m_bvp_y, pq_c, '0', mathml, 'ae', '')
```

Physical-Quantity x_i

```
>>> pq_x_i = pqh.create(m_bvp_y, "x_i")
>>> pqh.set_type(m_bvp_y, pq_x_i, "variable-parameter")
>>> dh.set_definition(m_bvp_y, pq_x_i, '0', p_x_i, 'assign', 'port')
```

Physical-Quantity y

```
>>> pq_y = pqh.create(m_bvp_y, "y")
>>> pqh.set_type(m_bvp_y, pq_y, "state")
>>> mathml = cstr2mml.cstr2mml('diff(y, time) = ( x_i - b * y + a )/c')
>>> dh.set_definition(m_bvp_y, pq_y, '0', mathml, 'ode', '')
>>> mathml = cstr2mml.cstr2mml('y = 0.2')
>>> dih.set_definition(m_bvp_y, pq_y, '0', mathml, 'ae')
>>> ph.set_reference(m_bvp_y, p_y, pq_y)
```

4. current_pulse_generator_membrane module

4.1 Make module and edit ports

Create “current_pulse_generator_membrane” module and output port “current”

```
>>> m_stim = mh.create("current_pulse_generator_membrane")
>>> p_current = ph.create(m_stim, "out", "current")
```

4.2 Edit physical-quantity

4.2.1 initial_current, pulse_height, pulse_onset_time and pulse_width

initial_current

```
>>> pq_initial = pqh.create(m_stim, "initial_current")
>>> pqh.set_type(m_stim, pq_initial, "static-parameter")
>>> pqh.set_description(m_stim, pq_initial, "The initial value of the stimulus current.")
>>> mathml = cstr2mml.cstr2mml('initial_current = 0')
>>> dh.set_definition(m_stim, pq_initial, '0', mathml, 'ae', '')
```

pulse_height

```
>>> pq_height = pqh.create(m_stim, "pulse_height")
>>> pqh.set_type(m_stim, pq_height, "static-parameter")
>>> pqh.set_description(m_stim, pq_height, "The pulse height.")
>>> mathml = cstr2mml.cstr2mml('pulse_height = 0.7')
>>> dh.set_definition(m_stim, pq_height, '0', mathml, 'ae', '')
```

pulse_onset_time

```
>>> pq_onset = pqh.create(m_stim, "pulse_onset_time")
>>> pqh.set_type(m_stim, pq_onset, "static-parameter")
>>> pqh.set_description(m_stim, pq_onset, "The time instance when the pulse takes place.")
>>> mathml = cstr2mml.cstr2mml('pulse_onset_time = 20')
>>> dh.set_definition(m_stim, pq_onset, '0', mathml, 'ae', '')
```

pulse_width

```
>>> pq_width = pqh.create(m_stim, "pulse_width")
>>> pqh.set_type(m_stim, pq_width, "static-parameter")
>>> pqh.set_description(m_stim, pq_width, "The pulse width in milli-second.")
>>> mathml = cstr2mml.cstr2mml('pulse_width = 40')
>>> dh.set_definition(m_stim, pq_width, '0', mathml, 'ae', '')
```


4.2.2 Set unit to pulse_onset_time and pulse_width

Get the unit-id of millisecond and define as uid_ms

```
>>> uid_ms = uh.get_id_with_name('millisecond')
```

Set milli second to *pulse_onset_time* and *pulse_width*

```
>>> pqh.set_unit(m_stim, pq_onset, uid_ms)
>>> pqh.set_unit(m_stim, pq_width, uid_ms)
```

4.2.3 Create stimulus_current

Create physical-quantity “stimulus_current” and set each property

```
>>> pq_stimulus = pqh.create(m_stim, "stimulus_current")
>>> pqh.set_type(m_stim, pq_stimulus, "variable-parameter")
```

Set implementation definition of stimulus_current

```
>>> csid = dh.set_definition(m_stim, pq_stimulus, '0', '', 'conditional', '')
>>> cid = dh.set_case(m_stim, pq_stimulus, csid, '0')
>>> mathml = cstr2mml.cstr2mml('pulse_onset_time <= time && time <= pulse_onset_time + pulse_width')
>>> dh.set_condition(m_stim, pq_stimulus, cid, mathml)
>>> mathml = cstr2mml.cstr2mml('stimulus_current = initial_current + pulse_height')
>>> dh.set_definition(m_stim, pq_stimulus, cid, mathml, 'ae', '')
>>> cid2 = dh.set_case(m_stim, pq_stimulus, csid, cid)
>>> mathml = cstr2mml.cstr2mml('stimulus_current = initial_current')
>>> dh.set_definition(m_stim, pq_stimulus, cid2, mathml, 'ae', '')
```

Bind physical-quantity to the output port y

```
>>> ph.set_reference(m_stim, p_current, pq_stimulus)
```

5. Link ports and Capsulation

5.1 Link ports

Link output port x (in BVP_excitation module) and input port y (in BVP_refractoriness module)

```
>>> bl.link_ports(m_bvp_x, p_x, m_bvp_y, p_x_i, "functional")
```

Link output port y (in BVP_refractoriness module) and input port x (in BVP_excitation module)

```
>>> bl.link_ports(m_bvp_y, p_y, m_bvp_x, p_y_i, "functional")
```

5.2 Capsulation

5.2.1. Capsulate current_pulse_generator_membrane module

Get module-id list of “current_pulse_generator_membrane”

```
>>> m_ids = mh.get_ids_with_name('current_pulse_generator_membrane')
>>> m_stim = m_ids[0]
```

Capsulate current_pulse_generator_membrane module

```
>>> mc_stim = bl.encapsulate(m_stim)
```

Create port “current” at capsule module of current_pulse_generator_membrane module

```
>>> pc_current = ph.create(mc_stim, 'out', 'current')
```

Link two current ports by forwarding edge

```
>>> bl.link_ports(m_stim, p_current, mc_stim, pc_current, 'forwarding')
```

5.2.2. Capsulate BVP_excitation and BVP_refractoriness modules

Get module-ids

```
>>> m_bvp_x = mh.get_ids_with_name('BVP_excitation')[0]
>>> m_bvp_y = mh.get_ids_with_name('BVP_refractoriness')[0]
```

Encapsulate BVP_excitation and BVP_refractoriness

```
>>> mc_bvp = bl.encapsulate([m_bvp_x, m_bvp_y])
```

Create port “Iext” at BVP capsule module

```
>>> pc_Iext = ph.create(mc_bvp, 'in', 'Iext')
```

Link two Iext ports by forwarding edge

```
>>> bl.link_ports(mc_bvp, pc_Iext, m_bvp_x, p_Iext, 'forwarding')
```

Create port “x” at capsule module of BVP_refractoriness module

```
>>> pc_x = ph.create(mc_bvp, 'out', 'x')
```

Link two x ports by forwarding edge

```
>>> bl.link_ports(m_bvp_x, p_x, mc_bvp, pc_x, 'forwarding')
```

5.3. Link capsule modules by functional edge

Link capsule modules by functional edge

```
>>> e_stim = bl.link_ports(mc_stim, pc_current, mc_bvp, pc_Iext, 'functional')
```

7. Couple two BVP models

Load sample/ bvp_pulse.isml

```
>>> model.load_new_isml_model('sample/SimulateWithISSim/bvp_pulse.isml')
```

7.1 Create gap_junction module

Make gap_junction module

```
>>> m_gap = mh.create('gap_junction')
```

Physical-Quantity k

```
>>> pq_k = pqh.create(m_gap, "k")
>>> pqh.set_type(m_gap, pq_k, "static-parameter")
>>> mathml = cstr2mml.cstr2mml("k = 0.6")
>>> dh.set_definition(m_gap, pq_k, "0", mathml, "ae", "")
```

Input port V_1 and physical-quantity V_1

```
>>> p_V_1 = ph.create(m_gap, 'in', 'V_1')
>>> pq_V_1 = pqh.create(m_gap, 'V_1')
>>> pqh.set_type(m_gap, pq_V_1, 'variable-parameter')
>>> dh.set_definition(m_gap, pq_V_1, '0', p_V_1, 'assign', 'port')
```

Input port V_2 and physical-quantity V_2

```
>>> p_V_2 = ph.create(m_gap, 'in', 'V_2')
>>> pq_V_2 = pqh.create(m_gap, 'V_2')
>>> pqh.set_type(m_gap, pq_V_2, 'variable-parameter')
>>> dh.set_definition(m_gap, pq_V_2, '0', p_V_2, 'assign', 'port')
```

Output port I_1 and physical-quantity I_1

```
>>> p_I_1 = ph.create(m_gap, 'out', 'I_1')
>>> pq_I_1 = pqh.create(m_gap, 'I_1')
>>> pqh.set_type(m_gap, pq_I_1, 'variable-parameter')
>>> mathml = cstr2mml.cstr2mml('I_1 = k * ( V_2 - V_1 )')
>>> dh.set_definition(m_gap, pq_I_1, '0', mathml, 'ae', '')
>>> ph.set_reference(m_gap, p_I_1, pq_I_1)
```

Output port I_2 and physical-quantity I_2

```
>>> p_I_2 = ph.create(m_gap, 'out', 'I_2')
>>> pq_I_2 = pqh.create(m_gap, 'I_2')
```

```

>>> pqh.set_type(m_gap, pq_I_2, 'variable-parameter')
>>> mathml = cstr2mml.cstr2mml('I_2 = k * ( V_1 - V_2 )')
>>> dh.set_definition(m_gap, pq_I_2, '0', mathml, 'ae', '')
>>> ph.set_reference(m_gap, p_I_2, pq_I_2)

```

7.2 Create sum module

Make sum module

```

>>> m_sum = mh.create('sum')

```

Input port Iarg_1 and physical-quantity I_1

```

>>> p_Iarg_1 = ph.create(m_sum, 'in', 'I_1')
>>> pq_Iarg_1 = pqh.create(m_sum, 'I_1')
>>> pqh.set_type(m_sum, pq_Iarg_1, 'variable-parameter')
>>> dh.set_definition(m_sum, pq_Iarg_1, '0', p_Iarg_1, 'assign', 'port')

```

Input port Iarg_2 and physical-quantity Iarg_2

```

>>> p_Iarg_2 = ph.create(m_sum, 'in', 'I_2')
>>> pq_Iarg_2 = pqh.create(m_sum, 'I_2')
>>> pqh.set_type(m_sum, pq_Iarg_2, 'variable-parameter')
>>> dh.set_definition(m_sum, pq_Iarg_2, '0', p_Iarg_2, 'assign', 'port')

```

Input port Isum and physical-quantity Isum

```

>>> p_sum = ph.create(m_sum, 'out', 'Isum')
>>> pq_sum = pqh.create(m_sum, 'Isum')
>>> pqh.set_type(m_sum, pq_sum, 'variable-parameter')
>>> mathml = cstr2mml.cstr2mml('Isum = I_1 + I_2')
>>> dh.set_definition(m_sum, pq_sum, '0', mathml, 'ae', '')
>>> ph.set_reference(m_sum, p_sum, pq_sum)

```

7.3 Copy BVP module

Copy BVP module and get the newly-created root module-id. The root module-id is overlap between newly-created module-id list and all root module-id list.

Set each ids

```

>>> mc_bvp = '19586a4d-e98f-48f8-8856-df42535602dd'
>>> pc_Iext = ph.get_ids(mc_bvp, "in")[0]
>>> e_stim = 'e45e8fe0-4997-433c-853c-748c51577b0f'
>>> m_bvp_x = '56f05090-c974-4d26-8f2e-debae430acfc'

```

```
>>> p_x = '3'
>>> mc_stim = '8798a6fa-420c-4d01-a8b5-f6705edd3b6b'
>>> pc_current = '1'
```

Delete functional edge between current and Iext

```
>>> bl.remove_edge(e_stim)
```

Create a new output port and link forwarding edge at BVP model

```
>>> pc_x = ph.create(mc_bvp, 'out')
>>> bl.link_ports(m_bvp_x, p_x, mc_bvp, pc_x, "forwarding")
```

Copy BVP module subtree and get root module-id of newly-created module subtree

```
>>> mc_bvp2 = bl.copy_subtree(mc_bvp, 'root')[0]
```

Get port-id of x and physical-quantity Iext in new BVP module

```
>>> pc_x2 = ph.get_ids(mc_bvp2, 'out')[0]
>>> pc_Iext2 = ph.get_ids(mc_bvp2, 'in')[0]
```

7.4 Link modules

Isum (sum) to port1 (capsule_of_BVP_refractoriness)

```
>>> bl.link_ports(m_sum, p_sum, mc_bvp, pc_Iext, 'functional')
```

port2 (capsule_of_BVP_refractoriness) to V_1 (gap_junction)

```
>>> bl.link_ports(mc_bvp, pc_x, m_gap, p_V_1, 'functional')
```

port2 (capsule_of_BVP_refractoriness__1) to V_2 (gap_junction)

```
>>> bl.link_ports(mc_bvp2, pc_x2, m_gap, p_V_2, 'functional')
```

I_1 (gap_junction) to I_1 (sum)

```
>>> bl.link_ports(m_gap, p_I_1, m_sum, p_Iarg_1, 'functional')
```

I_2 (gap_junction) to port_1 (capsule_of_BVP_refractoriness__1)

```
>>> bl.link_ports(m_gap, p_I_2, mc_bvp2, pc_Iext2, 'functional')
```

port_1 (capsule_of_current_pulse_generator_membrane) to I_2 (sum)

```
>>> bl.link_ports(mc_stim, pc_current, m_sum, p_Iarg_2, 'functional')
```